

Linux

Baremetal recovery starten op een server

Volg deze handleiding als je een baremetal restore wilt uitvoeren met Mihos.net Server Backup. In deze handleiding gaan we er vanuit dat er geen gebruik gemaakt wordt van DHCP, en je de server een publiek IPv4 adres toewijst.

1. Boot de server waar de backup naar hersteld moet worden met de onderstaande .iso:

https://faq.mihos.net/faq/index.php?solution_id=1152

2. Zodra je de server succesvol met de recovery iso hebt opgestart zal je onderstaand scherm zien.

```
[ 3.151876] ata12: SATA link down (SStatus 0 SControl 300)
[ 3.152227] ata11: SATA link down (SStatus 0 SControl 300)
[ 3.152613] ata24: SATA link down (SStatus 0 SControl 300)
[ 3.152929] ata14: SATA link down (SStatus 0 SControl 300)
[ 3.153236] ata18: SATA link down (SStatus 0 SControl 300)
[ 3.153542] ata21: SATA link down (SStatus 0 SControl 300)
[ 3.153986] ata8: SATA link down (SStatus 0 SControl 300)
[ 3.154307] ata15: SATA link down (SStatus 0 SControl 300)
[ 3.154712] ata22: SATA link down (SStatus 0 SControl 300)
[ 3.155065] ata3.00: ATAPI: VMware Virtual SATA CDRW Drive, 00000001, max UDMA/33
[ 3.155391] ata10: SATA link down (SStatus 0 SControl 300)
[ 3.155764] ata32: SATA link down (SStatus 0 SControl 300)
[ 3.156026] ata3.00: configured for UDMA/33
[ 3.156424] scsi 2:0:0:0: CD-ROM          NECVMWar VMware SATA CD00 1.00 PQ: 0 ANSI: 5
[ 3.156793] sr0: scsi3-mmc drive: 1x/1x writer dvd-ram cd/rw xa/form2 cdda tray
[ 3.157030] cdrom: Uniform CD-ROM driver Revision: 3.20
[ 3.157393] sr 2:0:0:0: Attached scsi generic sg1 type 5
[ 3.170685] usb 2-2: new full-speed USB device number 3 using uhci_hcd
[ 3.211728] input: ImPS/2 Generic Wheel Mouse as /devices/platform/i8042/serio1/input/input3
Welcome to Ubuntu 14.04.1 LTS (GNU/Linux 3.13.0-37-generic x86_64)

      _ _ _
     / / /
    / / /
   / / /
  / / /
 / / /
/_/_/_

Disaster Recovery -- Ubuntu Edition
Version             5.8.0 build x

configure network with "sudo ceni"
tty consoles are available by pressing Alt+(F1-F8)


* Ubuntu Help:  https://help.ubuntu.com/
* R1Soft Help:  http://wiki.r1soft.com
r1soft@r1soft:~$ _
```

Geef onderstaand commando op om de server een IP adres te geven.

sudo ceni


Onderstaand scherm zal getoond worden. Kies de bovenste netwerk interface, in onderstaand voorbeeld **eth0**.

Linux



Kies voor **Reconfigure eth0**.

Linux



Geef nu de juiste netwerk instellingen op en kies voor [**Accept**].

!! Belangrijk: weet je deze gegevens niet? Neem contact op met Mihos.net

Linux

Network Settings for eth0


Method <> dhcp <0> static	Class <> allow-hotplug (Removable Devices) <0> auto (Built-In Devices) <> manual	
IP Address ipv4 adres	Network ipv4 network adres	Gateway gateway ipv4 adres
Netmask 255.255.255.0	Broadcast ipv4 broadcast adres	DNS Search dit veld leeg laten
DNS Nameservers 1.1.1.1		

[Accept] [Back] [Cancel]

support !!

Kies voor [**Yes**].

Linux

A terminal window with a black background. A green rectangular box highlights a confirmation dialog. The dialog has a title bar that says "Do you want to exit?". Inside the box, it says "Select 'yes' to exit or 'no' to continue." At the bottom right of the box, there are two buttons: "< Yes >" and "< No >".

```
Do you want to exit?  
  
Select 'yes' to exit or 'no' to continue.  
  
< Yes > < No >
```

Type nu:

`sudo /etc/init.d/cdp-agent restart`

Je kan nu de baremetal restore starten via de Mihos.net Server Backup webinterface.

Unieke FAQ ID: #1197

Auteur: Erik

Laatst bijgewerkt: 2019-03-26 12:30